

# GUID Partition Table

---

- Unified Extensible Firmware Interface (UEFI)
- Master Boot Record (MBR)
- GUID Partition Table (GPT)

# Unified Extensible Firmware Interface

## ❑ Legacy BIOS limitations


- 16-bit processor mode
- 1 MB addressable space

## ❑ Advantages

- 32-bit/64-bit processor mode
- Ability to boot from larger disk with a GPT
- Flexible pre-OS environment, including network capability
- Modular design

## ❑ Compatibility Support Module (CSM)

- BIOS-MBR
- BIOS-GPT



# Master Boot Record (1/2)

---

- ❑ The Master Boot Record (MBR) is the first 512 bytes of a storage device

| Offset | Length    | Contents                            |
|--------|-----------|-------------------------------------|
| 0      | 446 bytes | Boot code area                      |
| 446    | 64 bytes  | Partition tables, each has 16 bytes |
| 510    | 2 bytes   | Boot signature (0xAA55)             |
| 128    | Total     |                                     |

# Master Boot Record (2/2)

---

## ❑ Drawbacks

- (4 primary partitions) or (3 primary + 1 extended partitions)
  - Arbitrary number of logical partitions within the extended partition
- The logical partition meta-data is stored in a linked-list structure
- One byte partition type codes which leads to many collisions
- Maximum addressable size is 2 TiB, i.e. any space beyond 2 TiB cannot be defined as a partition
  - MBR stores partition sector information using 32-bit LBA values
  - 512 bytes per sector
  - $2^{32} * 512 \text{ bytes} = 2 \text{ TiB}$

# Booting Process

---

1. System initialization with firmware called BIOS
2. The BIOS looks for the bootloader on the MBR, then executes it
3. Bootloader reads the partition table
  - Conventional Windows/DOS MBR bootloader search for one active and primary partition
  - GRUB safely ignores this
4. Loading operating system

# GUID Partition Table (1/9)

---

- ❑ GUID stands for Globally Unique Identifier
  - Ex: 3F2504E0-4F89-41D3-9A0C-0305E82C3301
- ❑ Part of the UEFI specification
- ❑ Solves some legacy problems with MBR but also may have compatibility issues
- ❑ Can be used also on BIOS system via a protective MBR

# GUID Partition Table (2/9)

---

## ❑ Advantages


- Filesystem-independent
- No partition type collision because of GUIDs
- 8 ZiB
  - GPT uses 64-bit LBA
  - 512 bytes per sector
  - $2^{64} * 512 \text{ bytes} = 8 \text{ ZiB}$
- Backup header and partition table at the end of the disk
- CRC32 checksums for header and partition table

# GUID Partition Table (3/9)

## □ GPT Scheme

- LBA 0: Legacy MBR
- LBA 1: GPT header
- LBA 2~33: Partition entries
  - Up to 128 partitions
- LBA 34~: Partitions
- LBA -34~-1: Secondary GPT data

## GUID Partition Table Scheme





# GUID Partition Table (4/9)

---

## ❑ Legacy MBR (LBA 0)

- A single partition type of 0xEE
- For OSes cannot read GPT disks: Unknown type, no empty space
- For GPT-aware OSes: check the protective MBR

# GUID Partition Table (5/9)

## ❑ GPT header (LBA 1)

| Offset | Length   | Contents   |
|--------|----------|--|
| 0      | 8 bytes  | Signature (" <b>EFI PART</b> ", 45 46 49 20 50 41 52 54)   |
| 8      | 4 bytes  | Revision (For GPT version 1.0 (through at least UEFI version 2.3.1), the value is <b>00 00 01 00</b> ) |
| 12     | 4 bytes  | Header size in little endian (in bytes, usually <b>5C 00 00 00</b> meaning 92 bytes)                   |
| 16     | 4 bytes  | <b>CRC32</b> of header (0 to header size), with this field zeroed during calculation                   |
| 20     | 4 bytes  | Reserved; must be <b>zero</b>  |
| 24     | 8 bytes  | <b>Current LBA</b> (location of this header copy)  |
| 32     | 8 bytes  | <b>Backup LBA</b> (location of the other header copy)  |
| 40     | 8 bytes  | <b>First usable LBA</b> for partitions (primary partition table last LBA + 1)                          |
| 48     | 8 bytes  | <b>Last usable LBA</b> (secondary partition table first LBA - 1)                                       |
| 56     | 16 bytes | Disk GUID (also referred as UUID on UNIXes)  |
| 72     | 8 bytes  | Partition entries starting LBA (always 2 in primary copy)  |
| 80     | 4 bytes  | Number of partition entries  |
| 84     | 4 bytes  | Size of a partition entry (usually 128)  |
| 88     | 4 bytes  | CRC32 of partition array   |
| 92     | *        | Reserved; must be zeroes for the rest of the block (420 bytes for a 512-byte LBA)                      |

# GUID Partition Table (6/9)

## ❑ GPT header (LBA 1)

- `dd if=/dev/ada0 bs=512 count=1 skip=1 | hd`

```
# dd if=/dev/ada0 bs=512 count=1 skip=1 | hd
00000000  45 46 49 20 50 41 52 54 00 00 01 00 5c 00 00 00 |EFI PART....\...|
00000010  ad 09 1d 1d 00 00 00 00 01 00 00 00 00 00 00 00 |.....|
00000020  ff ff 7f 02 00 00 00 00 22 00 00 00 00 00 00 00 |.....".....|
00000030  de ff 7f 02 00 00 00 00 65 67 3c f3 ea 40 e4 11 |.....eg<..@..|
00000040  a2 27 55 0b 19 3d b4 a4 02 00 00 00 00 00 00 00 |.'U..=.....|
00000050  80 00 00 00 80 00 00 00 82 f4 3d 77 00 00 00 00 |.....=w....|
00000060  00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 |.....|
*
00000200
```

# GUID Partition Table (7/9)

## ❑ Partition entries (LBA 2)

| Offset | Length    | Contents  |
|--------|-----------|---|
| 0      | 16 bytes  | <b>Partition type</b> GUID                      |
| 16     | 16 bytes  | Unique partition GUID                           |
| 32     | 8 bytes   | <b>First LBA</b> (little-endian)                |
| 40     | 8 bytes   | <b>Last LBA</b> (inclusive, usually odd)        |
| 48     | 8 bytes   | Attribute flags (e.g. bit 60 denotes read-only) |
| 56     | 72 bytes  | <b>Partition name</b> (36 UTF-16LE code units)  |
|        | 128 bytes | Total   |

# GUID Partition Table (8/9)

---

## ❑ Partition type GUID

|               |                                      |
|---------------|--------------------------------------|
| freebsd-boot  | 83BD6B9D-7F41-11DC-BE0B-001560B84F0F |
| freebsd       | 516E7CB4-6ECF-11D6-8FF8-00022D09712B |
| freebsd-swap  | 516E7CB5-6ECF-11D6-8FF8-00022D09712B |
| freebsd-ufs   | 516E7CB6-6ECF-11D6-8FF8-00022D09712B |
| freebsd-vinum | 516E7CB8-6ECF-11D6-8FF8-00022D09712B |
| freebsd-zfs   | 516E7CBA-6ECF-11D6-8FF8-00022D09712B |

# GUID Partition Table (9/9)

## □ Partition entries (LBA 2)

- `dd if=/dev/ada0 bs=512 count=1 skip=2 | hd`

```
# dd if=/dev/ada0 bs=512 count=1 skip=2 | hd
00000000  9d 6b bd 83 41 7f dc 11  be 0b 00 15 60 b8 4f 0f  |.k..A.....`.O.|
00000010  0e 99 e2 03 eb 40 e4 11  a2 27 55 0b 19 3d b4 a4  |.....@...'U..=..|
00000020  22 00 00 00 00 00 00 00  a1 00 00 00 00 00 00 00  |".....|
00000030  00 00 00 00 00 00 00 00  00 00 00 00 00 00 00 00  |.....|
*
00000080  b5 7c 6e 51 cf 6e d6 11  8f f8 00 02 2d 09 71 2b  |.|nQ.n.....-.q+|
00000090  98 66 a7 0f eb 40 e4 11  a2 27 55 0b 19 3d b4 a4  |.f...@...'U..=..|
000000a0  a2 00 00 00 00 00 00 00  a1 00 20 00 00 00 00 00  |.....|
000000b0  00 00 00 00 00 00 00 00  73 00 77 00 61 00 70 00  |.....s.w.a.p.|
000000c0  2d 00 30 00 00 00 00 00  00 00 00 00 00 00 00 00  |-.0.....|
000000d0  00 00 00 00 00 00 00 00  00 00 00 00 00 00 00 00  |.....|
*
00000100  ba 7c 6e 51 cf 6e d6 11  8f f8 00 02 2d 09 71 2b  |.|nQ.n.....-.q+|
00000110  f6 11 10 1b eb 40 e4 11  a2 27 55 0b 19 3d b4 a4  |.....@...'U..=..|
00000120  a2 00 20 00 00 00 00 00  de ff 7f 02 00 00 00 00  |..|
00000130  00 00 00 00 00 00 00 00  7a 00 66 00 73 00 2d 00  |.....z.f.s.-|
00000140  30 00 00 00 00 00 00 00  00 00 00 00 00 00 00 00  |0.....|
00000150  00 00 00 00 00 00 00 00  00 00 00 00 00 00 00 00  |.....|
*
00000200
```

# References

---

- ❑ <http://pansci.tw/archives/8111>
- ❑ <http://www.rodsbooks.com/gdisk/whatsgpt.html>